



Hewlett Packard
Enterprise

HPE Security ArcSight Connectors

SmartConnector for Bro IDS NG File

Configuration Guide

November 30, 2016

Configuration Guide

SmartConnector for Bro IDS NG File

November 30, 2016

Copyright © 2006 – 2016 Hewlett Packard Enterprise Development LP

Warranty

The only warranties for Hewlett Packard Enterprise products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. Hewlett Packard Enterprise Development LP shall not be liable for technical or editorial omissions contained herein. The information contained herein is subject to change without notice. The network information used in the examples in this document (including IP addresses and hostnames) is for illustration purposes only. Hewlett Packard Enterprise Development LP products are highly flexible and function as you configure them. The accessibility, integrity, and confidentiality of your data is your responsibility. Implement a comprehensive security strategy and follow good security practices. This document is confidential.

Restricted Rights Legend

Confidential computer software. Valid license from Hewlett Packard Enterprise Development LP required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

Follow this link to see a complete statement of Hewlett Packard Enterprise Development LP copyrights, trademarks and acknowledgements:

<https://www.protect724.hpe.com/docs/DOC-13026>.

Revision History

Date	Description
11/30/2016	Updated installation procedure for setting preferred IP address mode.
02/15/2015	Updated parameters screenshot and table to describe Bro IDS Host Name parameter. Removed host name configuration from the Configuration section.
03/31/2015	Corrected errors in parameters table. Added support for v2.3. Added the following mappings tables: dhcp, files, known_certs, known_hosts, known_services, loaded scripts, and x509.
02/14/2014	Updated parameter screen image.
09/30/2013	Updated mappings.
06/28/2013	Updated HTTP mappings table.
03/29/2013	First edition of this Configuration Guide.

Contents

Product Overview.....	4
Configuration.....	4
Loading Policy Scripts.....	5
Install the SmartConnector.....	5
Prepare to Install Connector	5
Install Core Software.....	6
Set Global Parameters (optional).....	7
Select Connector and Add Parameter Information.....	7
Select a Destination	8
Complete Installation and Configuration	9
Run the SmartConnector	9
Device Event Mapping to ArcSight Fields	9
Bro IDS Communication Log Mappings	10
Bro IDS Conn Log Mappings	10
Bro IDS DHCP Log Mappings.....	11
Bro IDS DNS Log Mappings	11
Bro IDS DPD Log Mappings	12
Bro IDS Files Log Mappings	12
Bro IDS FTP Log Mappings	13
Bro IDS HTTP Log Mappings.....	13
Bro IDS Known Certificates Log Mappings	14
Bro IDS Known Hosts Log Mappings.....	15
Bro IDS Known Services Log Mappings	15
Bro IDS Loaded Scripts Log Mappings	15
Bro IDS Notice Log Mappings.....	16
Bro IDS Packet Filter Log Mappings	16
Bro IDS Reporter Log Mappings	17
Bro IDS SMTP Log Mappings	17
Bro IDS Software Log Mappings.....	18
Bro IDS SSH Log Mappings.....	18
Bro IDS SSL Log Mappings	19
Bro IDS Tunnel Log Mappings.....	19
Bro IDS Weird Log Mappings.....	20
Bro IDS x509 Module Log Mappings	20

SmartConnector for Bro IDS NG File

This guide provides information for installing the SmartConnector for Bro IDS NG File and configuring the device for event collection. Bro IDS Versions 2.1 and 2.3 are supported.

Product Overview

Bro is a Unix-based Network Intrusion Detection System (IDS). Bro monitors network traffic and detects intrusion attempts based upon the traffic characteristics and content.

Bro detects intrusions by comparing network traffic against rules describing events that are deemed troublesome. These rules might describe activities (for example, certain hosts connecting to certain services), what activities are worth alerting (for example, attempts to a given number of different hosts constitutes a "scan"), or signatures describing known attacks or access to known vulnerabilities.

If Bro detects something of interest, it can be instructed either to issue a log entry or to initiate the execution of an operating system command.

Configuration

The Bro configuration file is `$BROHOME/usr/local/bro/etc/bro.cfg`. To reconfigure Bro, run `$BROHOME/scripts/bro_config`. This updates your Bro configuration (`$BROHOME/usr/local/bro/etc/bro.cfg`) file. You can also edit this file using your favorite editor.

The directory in which log files are located is:

```
$BROHOME/usr/local/bro/logs
```

The bro logs take the form:

```
type.hostname.start_date/time-end_date/time
```

where `type` is the log file type.

The following log types are supported by the Bro IDS NG SmartConnector:

Log Type	Description
communication	A record of every communication Bro performs.
conn	A record of every connection Bro detects.
dhcp	DHCP-related alerts.
dns	DNS-related alerts.
dpd	DPD-related alerts.
files	file-related alerts.
ftp	All session activity involving the ftp control port.
http	All session activity involving the http ports.
known_certs	All session activity involving recognized certificates.
known_hosts	All session activity involving recognized hosts.
known_services	All session activity involving recognized services.

Log Type	Description
loaded_scripts	All session activity involving loaded scripts.
notice	Network occurrences that are determined to be of nominal importance.
packet_filter	All session activity involving packet filtering.
reporter	All session activity generating reports.
smtp	All session activity involving the smtp port.
software	All session activity involving software.
ssh	SSH-related alerts.
ssl	SSL-related alerts.
tunnel	All session activity involving tunnels.
weird	A record of instances of network traffic that simply should not happen.
x509	All session activity involving module X509.

Loading Policy Scripts

The following policy scripts included with Bro for generating log files are on by default:

conn, ftp, http, smtp, weird, notice



The Bro distribution includes a number of standard Notices, controlled by a number of different policies. To get a list of all notices that your Bro configuration might generate, enter `'sh . $BROHOME/etc/bro.cfg; bro -z notice $BRO_HOSTNAME.bro'`

The following policy scripts are not loaded by default. You should add these to your `$BROHOME/site/brohost.bro` policy file for the log files to be generated.

communication, dns, dpd, packet_filter, reporter, software, ssh, ssl, tunnel

Install the SmartConnector

The following sections provide instructions for installing and configuring your selected SmartConnector.



Connector Appliance/ArcSight Management Center supports mounting for Network File System (NFS) and CIFS (Windows) shares. When you install this connector on one of these devices, establish a CIFS mount on the device before adding the connector. Provide this share name during connector configuration. For more information, see **Remote File Systems** in the Connector Appliance or ArcSight Management Center Administrator's Guide.

Prepare to Install Connector

Before you install any SmartConnectors, make sure that the ArcSight products with which the connectors will communicate have already been installed correctly (such as ArcSight ESM or ArcSight Logger). This configuration guide takes you through the installation process with **ArcSight Manager (encrypted)** as the destination.

For complete product information, read the *Administrator's Guide* as well as the *Installation and Configuration* guide for your ArcSight product before installing a new SmartConnector. If you are adding a connector to the ArcSight Management Center, see the *ArcSight Management Center*

Administrator's Guide for instructions, and start the installation procedure at "Set Global Parameters (optional)" or "Select Connector and Add Parameter Information."

Before installing the SmartConnector, be sure the following are available:

- Local access to the machine where the SmartConnector is to be installed
- Administrator passwords

Install Core Software


Unless specified otherwise at the beginning of this guide, this SmartConnector can be installed on all ArcSight supported platforms; for the complete list, see the *SmartConnector Product and Platform Support* document, available from the HPE SSO and Protect 724 sites.

- 1 Download the SmartConnector executable for your operating system from the HPE SSO site.
- 2 Start the SmartConnector installation and configuration wizard by running the executable.

Follow the wizard through the following folder selection tasks and installation of the core connector software:

Introduction
Choose Install Folder
Choose Shortcut Folder
Pre-Installation Summary
Installing...

- 3 When the installation of SmartConnector core component software is finished, the following window is displayed:



Set Global Parameters (optional)


If you choose to perform any of the operations shown in the following table, do so before adding your connector. After installing core software, you can set the following parameters:

Global Parameter	Setting
Set FIPS mode	Set to 'Enable' to enable FIPS compliant mode. To enable FIPS Suite B Mode, see the SmartConnector User Guide under "Modifying Connector Parameters" for instructions. Initially, this value is set to 'Disable'.
Set Remote Management	Set to 'Enable' to enable remote management from ArcSight Management Center. When queried by the remote management device, the values you specify here for enabling remote management and the port number will be used. Initially, this value is set to 'Disable'.
Remote management listener port	The remote management device will listen to the port specified in this field. The default port number is 9001.
Preferred IP Version	If both 'IPv4' and 'IPv6' IP addresses are available for the local host (the machine on which the connector is installed), you can choose which version is preferred. Otherwise, you will see only one selection. When both values are present, the initial setting is 'IPv4'.

After making your selections, click **Next**. A summary screen is displayed. Review the summary of your selections and click **Next**. Click **Continue** to return to the "Add a Connector" window. Continue the installation procedure with "Select Connector and Add Parameter Information."

Select Connector and Add Parameter Information

- 1 Select **Add a Connector** and click **Next**. If applicable, you can enable FIPS mode and enable remote management later in the wizard after SmartConnector configuration.
- 2 Select **Bro IDS NG File** and click **Next**.
- 3 Enter the required SmartConnector parameters to configure the SmartConnector, then click **Next**.



Parameter	Description
Log Folder	Enter the location of the directory in which log files are kept, or accept the default value of \$BROHOME/usr/local/bro/logs.
Selected Log Types	Select any or all of the following SmartConnector-supported log types: communication, conn, dhcp, dns, dpd, files, ftp, http, known_certs, known_hosts, known_services, loaded_scripts, notice, packet_filter, reporter, smtp, ssh, ssl, tunnel, weird, x509. Note that the policies for DNS, SSH, and SSL are not automatically loaded by default; you must load them manually for their log files to be generated. See "Loading Policy Scripts."
Bro IDS Host Name	Enter host name of the machine containing the Bro IDS File logs. This value is mapped to the event.deviceHostName field.

Select a Destination

- 1 The next window asks for the destination type; make sure **ArcSight Manager (encrypted)** is selected and click **Next**. (For information about this destination or any of the other destinations listed, see the *ArcSight SmartConnector User Guide*.)
- 2 Enter values for the **Manager Host Name**, **Manager Port**, **User** and **Password** required parameters. This is the same ArcSight user name and password you created during the ArcSight Manager installation. Click **Next**.
- 3 Enter a name for the SmartConnector and provide other information identifying the connector's use in your environment. Click **Next**. The connector starts the registration process.
- 4 The certificate import window for the ArcSight Manager is displayed. Select **Import the certificate to the connector from destination** and click **Next**. (If you select **Do not import the certificate to connector from destination**, the connector installation will end.) The certificate is imported and the **Add connector Summary** window is displayed.

Complete Installation and Configuration

- 1 Review the **Add Connector Summary** and click **Next**. If the summary is incorrect, click **Previous** to make changes.
- 2 The wizard now prompts you to choose whether you want to run the SmartConnector as a stand-alone process or as a service. If you choose to run the connector as a stand-alone process, select **Leave as a standalone application**, click **Next**, and continue with step 5.
- 3 If you chose to run the connector as a service, with **Install as a service** selected, click **Next**. The wizard prompts you to define service parameters. Enter values for **Service Internal Name** and **Service Display Name** and select **Yes** or **No** for **Start the service automatically**. The **Install Service Summary** window is displayed when you click **Next**.
- 4 Click **Next** on the summary window.
- 5 To complete the installation, choose **Exit** and Click **Next**.

For some SmartConnectors, a system restart is required before the configuration settings you made take effect. If a **System Restart** window is displayed, read the information and initiate the system restart operation.



Save any work on your computer or desktop and shut down any other running applications (including the ArcSight Console, if it is running), then shut down the system.

For instructions about upgrading the connector or modifying parameters, see the *SmartConnector User Guide*.

Run the SmartConnector

SmartConnectors can be installed and run in stand-alone mode, on Windows platforms as a Windows service, or on UNIX platforms as a UNIX daemon, depending upon the platform supported. On Windows platforms, SmartConnectors also can be run using shortcuts and optional Start menu entries.

If the connector is installed in stand-alone mode, it must be started manually and is not automatically active when a host is restarted. If installed as a service or daemon, the connector runs automatically when the host is restarted. For information about connectors running as services or daemons, see the *ArcSight SmartConnector User Guide*.

To run all SmartConnectors installed in stand-alone mode on a particular host, open a command window, go to `$ARCSIGHT_HOME\current\bin` and run: `arcsight connectors`

To view the SmartConnector log, read the file `$ARCSIGHT_HOME\current\logs\agent.log`; to stop all SmartConnectors, enter `Ctrl+C` in the command window.

Device Event Mapping to ArcSight Fields

The following section lists the mappings of ArcSight data fields to the device's specific event definitions. See the *ArcSight Console User's Guide* for more information about the ArcSight data fields.

Bro IDS Communication Log Mappings

ArcSight ESM Field	Device-Specific Field
Agent (Connector) Severity	High = error; Medium = warning; Low = info
Device Custom String 2	src_name
Device Custom String 4	peer
Device Event Category	communication
Device Event Class Id	communication
Device Product	'Bro'
Device Receipt Time	ts
Device Severity	level
Device Vendor	'Bro'
Message	message
Name	communication

Bro IDS Conn Log Mappings

ArcSight ESM Field	Device-Specific Field
Agent (Connector) Severity	medium = REJ; low = S0, S1, SF, S2, S3, RSTO, RSTR, RSTOS0, RSTRH, SH, SHR, OTH
Application Protocol	service
Bytes In	resp_bytes
Bytes Out	orig_bytes
Destination Address	id.resp_h
Destination Port	id.resp_p
Device Custom IPv6 Address 2	Source IPv6 Address
Device Custom IPv6 Address 3	Destination IPv6 Address
Device Custom Number 1	Missed bytes
Device Custom Number 2	Original IP bytes
Device Custom Number 3	Responder IP Bytes
Device Custom String 3	Connection ID
Device Custom String 4	Connection Duration
Device Event Category	conn
Device Event Class Id	conn_state
Device Product	'Bro'
Device Receipt Time	ts
Device Severity	conn_state
Device Vendor	'Bro'
Name	conn
Source Address	id.orig_h
Source Port	id.orig_p
Transport Protocol	proto

Bro IDS DHCP Log Mappings

ArcSight ESM Field	Device-Specific Field
Agent (Connector) Severity	low = Low
Destination Address	id.resp_h
Destination Port	id.resp_p
Device Address	assigned_ip
Device Custom Number 1	Transaction ID
Device Custom String 3	Connection ID
Device Custom String 4	Lease Time
Device Event Category	dhcp
Device Event Class Id	DHCP Lease
Device Product	'Bro'
Device Receipt Time	ts
Device Severity	Low
Device Vendor	'Bro'
Name	DHCP Lease
Source Address	id.orig_h
Source MAC Address	mac
Source Port	id.orig_p

Bro IDS DNS Log Mappings

ArcSight ESM Field	Device-Specific Field
Agent (Connector) Severity	low = Low
Destination Address	id.resp_h
Destination DNS Domain	query
Destination Port	id.resp_p
Device Custom IPv6 Address 2	Source IPv6 Address
Device Custom IPv6 Address 3	Destination IPv6 Address
Device Custom Number 1	Transaction ID
Device Custom String 1	Query Type Name
Device Custom String 3	uid
Device Custom String 4	qclass_name
Device Event Category	dns
Device Event Class Id	qtype
Device Product	'Bro'
Device Receipt Time	ts
Device Severity	Low
Device Vendor	'Bro'
Event Outcome	rejected
Message	All of (answers, Domain Name System Events, answers)
Name	One of (qtype_name, DNS - No Query)
Source Address	id.orig_h
Source Port	id.orig_p

ArcSight ESM Field	Device-Specific Field
Transport Protocol	proto

Bro IDS DPD Log Mappings

ArcSight ESM Field	Device-Specific Field
Agent (Connector) Severity	low = Low
Application Protocol	analyzer
Destination Address	id.resp_h
Destination Port	id.resp_p
Device Custom IPv6 Address 2	Source IPv6 Address
Device Custom IPv6 Address 3	Destination IPv6 Address
Device Custom String 3	Connection ID
Device Event Category	'dpd'
Device Event Class Id	All of ('dpd:', analyzer)
Device Product	'Bro'
Device Receipt Time	ts
Device Severity	Low
Device Vendor	'Bro'
Message	failure_reason
Name	All of ('dpd:', analyzer, 'Analyzer')
Source Address	id.orig_h
Source Port	id.orig_p
Transport Protocol	proto

Bro IDS Files Log Mappings

ArcSight ESM Field	Device-Specific Field
Agent (Connector) Severity	low = Low
Bytes In	total_bytes
Bytes Out	overflow_bytes
Destination Host Name	rx_hosts
Device Custom String 2	Parent File ID
Device Custom String 3	Connection ID
Device Custom String 4	File Analysis Duration
Device Custom String 5	Analyzers
Device Event Category	files
Device Event Class Id	Files Analysis
Device Product	'Bro'
Device Receipt Time	ts
Device Severity	Low
Device Vendor	'Bro'
File Hash	sha1
File ID	fuid
File Name	filename

ArcSight ESM Field	Device-Specific Field
File Path	source
File Type	mime_type
Name	Files Analysis
Source Host Name	tx_hosts

Bro IDS FTP Log Mappings

ArcSight ESM Field	Device-Specific Field
Agent (Connector) Severity	low = Low
Destination Address	One of (id.resp_h, data_channel.resp_h)
Destination Port	id.resp_p
Device Action	command
Device Custom IPv6 Address 2	Source IPv6 Address
Device Custom IPv6 Address 3	Destination IPv6 Address
Device Custom Number 1	Data Channel Response Port
Device Custom String 3	Connection ID
Device Event Category	ftp
Device Event Class Id	reply_code
Device Product	'Bro'
Device Receipt Time	ts
Device Severity	Low
Device Vendor	'Bro'
Event Outcome	data_channel.passive
File ID	fuid
File Size	file_size
File Type	mime_type
Message	reply_msg
Source Address	One of (id.orig_h, data_channel.orig_h)
Source Port	id.orig_p
Source User Name	user

Bro IDS HTTP Log Mappings

ArcSight ESM Field	Device-Specific Field
Agent (Connector) Severity	high = 400 – 599; Medium = 300 – 399; Low = 0 – 299
Bytes In	request_body_len
Bytes Out	response_body_len
Destination Address	id.resp_h
Destination Port	id.resp_p
Device Custom IPv6 Address 2	Source IPv6 Address
Device Custom IPv6 Address 3	Destination IPv6 Address
Device Custom String 2	Origin File Unique Identifier
Device Custom String 3	Connection ID
Device Custom String 4	Referrer

ArcSight ESM Field	Device-Specific Field
Device Custom String 5	User Agent
Device Custom String 6	Response File Unique Identifier
Device Event Category	'http'
Device Event Class Id	Both("http:",method)
Device Product	'Bro'
Device Receipt Time	ts
Device Severity	One of (status_code, 0)
Device Vendor	'Bro'
File Name	filename
File Type	One of (orig_mime_types,resp_mime_types)
Message	status_msg
Name	Both('http:', status_msg)
Request Client Application	user-agent
Request Context	referrer
Request Method	method
Request Protocol	http
Request URL Authority	All of (username, password, host, id.resp_h, id.resp_p)
Request URL File Name	uri
Request URL Host	One of (host, id.resp_h)
Request URL Port	id.resp_p
Request URL Query	uri
Source Address	id.orig_h
Source Port	id.orig_p
Source User Name	username

Bro IDS Known Certificates Log Mappings

ArcSight ESM Field	Device-Specific Field
Agent (Connector) Severity	low = Low
Device Custom String 3	Issuer Subject
Device Custom String 4	Certificate Serial Number
Device Event Category	known_certs
Device Event Class Id	Certificates Information
Device Product	'Bro'
Device Receipt Time	ts
Device Severity	Low
Device Vendor	'Bro'
Message	subject
Name	Certificates Information
Source Address	host
Source Port	port_num

Bro IDS Known Hosts Log Mappings

ArcSight ESM Field	Device-Specific Field
Agent (Connector) Severity	low = Low
Device Event Category	known_hosts
Device Event Class Id	TCP Handshakes Host
Device Product	'Bro'
Device Receipt Time	ts
Device Severity	Low
Device Vendor	'Bro'
Name	TCP Handshakes Host
Source Address	host

Bro IDS Known Services Log Mappings

ArcSight ESM Field	Device-Specific Field
Agent (Connector) Severity	low = Low
Application Protocol	service
Device Event Category	known_services
Device Event Class Id	Service Tracking
Device Product	'Bro'
Device Receipt Time	ts
Device Severity	Low
Device Vendor	'Bro'
Name	Service Tracking
Source Address	host
Source Port	port_number
Transport	port_proto

Bro IDS Loaded Scripts Log Mappings

ArcSight ESM Field	Device-Specific Field
Agent (Connector) Severity	low = Low
Device Event Category	loaded_scripts
Device Event Class Id	Loaded Script
Device Product	'Bro'
Device Severity	Low
Device Vendor	'Bro'
File Name	name
Message	name
Name	Loaded Script

Bro IDS Notice Log Mappings

ArcSight ESM Field	Device-Specific Field
Agent (Connector) Severity	low = Low
Destination Address	id.resp_h
Destination Port	id.resp_p
Device Custom Floating Point 1	Suppress Time
Device Custom IPv6 Address 2	Source IPv6 Address
Device Custom IPv6 Address 3	Destination IPv6 Address
Device Custom Number 1	Policy Items
Device Custom String 3	Connection ID
Device Custom String 4	Peer
Device Custom String 5	File Description
Device Event Category	'notice'
Device Event Class Id	actions
Device Product	'Bro'
Device Receipt Time	ts
Device Severity	Low
Device Vendor	'Bro'
File ID	fuid
File Type	file_mime_type
Message	msg
Name	note
Source Address	id.orig_h
Source Port	id.orig_p
Transport Protocol	proto

Bro IDS Packet Filter Log Mappings

ArcSight ESM Field	Device-Specific Field
Agent (Connector) Severity	low = Low
Device Custom String 4	Node
Device Event Category	'packet_filter'
Device Event Class Id	All of ('PacketFilter::', 'init', init, 'success', success)
Device Product	'Bro'
Device Receipt Time	ts
Device Severity	Low
Device Vendor	'Bro'
Message	filter
Name	All of ('Filter init', init, 'filter applied', success)

Bro IDS Reporter Log Mappings

ArcSight ESM Field	Device-Specific Field
Agent (Connector) Severity	high = ERROR; medium = WARNING; low = INFO
Device Event Category	reporter
Device Event Class Id	level
Device Product	'Bro'
Device Receipt Time	ts
Device Severity	level
Device Vendor	'Bro'
File Name	location
File Path	location
Message	level
Name	Message

Bro IDS SMTP Log Mappings

ArcSight ESM Field	Device-Specific Field
Agent (Connector) Severity	low = Low
Destination Address	id.resp_h
Destination Port	id.resp_p
Destination User Name	rcptto
Device Custom IPv6 Address 2	Source IPv6 Address
Device Custom IPv6 Address 3	Destination IPv6 Address
Device Custom Number 1	Transaction Depth
Device Custom String 2	Time To Live Service
Device Custom String 3	Connection ID
Device Custom String 4	Network Path
Device Custom String 5	Unique File Identifier
Device Event Category	smtp
Device Event Class Id	last_reply
Device Product	'Bro'
Device Receipt Time	ts
Device Severity	Low
Device Vendor	'Bro'
Message	last_reply
Source Address	id.orig_h
Source Port	id.orig_p
Source User Name	mailfrom

Bro IDS Software Log Mappings

ArcSight ESM Field	Device-Specific Field
Agent (Connector) Severity	low = Low
Device Custom IPv6 Address 2	Source IPv6 Address
Device Custom String 3	Version Major
Device Custom String 4	Version Minor
Device Custom String 5	Version Addition
Device Event Category	software
Device Event Class Id	software_type
Device Product	'Bro'
Device Receipt Time	ts
Device Severity	Low
Device Vendor	'Bro'
Message	unparsed_version
Name	name
Source Address	host
Source Port	host_p

Bro IDS SSH Log Mappings

ArcSight ESM Field	Device-Specific Field
Agent (Connector) Severity	low = Low
Bytes Out	resp_size
Destination Address	id.resp_h
Destination Port	id.resp_p
Device Custom IPv6 Address 2	Source IPv6 Address
Device Custom IPv6 Address 3	Destination IPv6 Address
Device Custom String 3	Connection ID
Device Custom String 4	Server Software
Device Custom String 5	Client Software
Device Direction	direction
Device Event Category	ssh
Device Event Class Id	All of ('ssh:', direction, status)
Device Product	'Bro'
Device Receipt Time	ts
Device Severity	Low
Device Vendor	'Bro'
Name	All of ('ssh:', direction, status)
Source Address	id.orig_h
Source Port	id.orig_p

Bro IDS SSL Log Mappings

ArcSight ESM Field	Device-Specific Field
Agent (Connector) Severity	low = Low
Destination Address	id.resp_h
Destination Host Name	subject (Common Name)
Destination Port	id.resp_p
Device Custom Date 1	Server Certificate Start Time
Device Custom Date 2	Server Certificate End Time
Device Custom IPv6 Address 2	Source IPv6 Address
Device Custom IPv6 Address 3	Destination IPv6 Address
Device Custom String 1	Client Issuer
Device Custom String 2	SSL/TLS Version
Device Custom String 3	Connection ID
Device Custom String 4	SSL/TLS Cipher Suite
Device Custom String 5	Validation Status
Device Custom String 6	Organizational Unit
Device Event Category	ssl
Device Event Class ID	SSL Session
Device Product	'Bro'
Device Receipt Time	ts
Device Severity	Low
Device Vendor	'Bro'
Event Outcome	established
External ID	session_id
File Path	subject (Common Name)
Message	subject
Name	SSL Session
Source Address	id.orig_h
Source Port	id.orig_p
Source User Name	client_subject

Bro IDS Tunnel Log Mappings

ArcSight ESM Field	Device-Specific Field
Agent (Connector) Severity	low = Low
Destination Address	id.resp_h
Destination Port	id.resp_p
Device Action	action
Device Custom IPv6 Address 2	Source IPv6 Address
Device Custom IPv6 Address 3	Destination IPv6 Address
Device Custom String 3	Connection ID
Device Event Category	'tunnel'
Device Event Class Id	action
Device Product	'Bro'

ArcSight ESM Field	Device-Specific Field
Device Receipt Time	ts
Device Severity	Low
Device Vendor	'Bro'
Name	tunnel_type
Source Address	id.orig_h
Source Port	id.orig_p

Bro IDS Weird Log Mappings

ArcSight ESM Field	Device-Specific Field
Agent (Connector) Severity	low = Low
Destination Address	id.resp_h
Destination Event Category	weird
Destination Port	id.resp_p
Device Custom IPv6 Address 2	Source IPv6 Address
Device Custom IPv6 Address 3	Destination IPv6 Address
Device Custom String 3	Connection ID
Device Custom String 4	Peer
Device Event Class Id	name
Device Product	'Bro'
Device Receipt Time	ts
Device Severity	Low
Device Vendor	'Bro'
Message	name
Name	name
Source Address	id.orig_h
Source Port	id.orig_p

Bro IDS x509 Module Log Mappings

ArcSight ESM Field	Device-Specific Field
Agent (Connector) Severity	low = Low
Destination Event Category	x509
Device Custom Date 1	Certificate is not valid before
Device Custom Date 2	Certificate is not valid after
Device Custom String 3	certificate.issuer (Certificate Issuer)
Device Event Class Id	x509
Device Product	'Bro'
Device Receipt Time	ts
Device Severity	Low
Device Vendor	'Bro'
File ID	id
Message	certificate.subject
Name	x509