

Release Notes for ArcSight Forwarding Connector

v5.1.7.6154.0 for ArcSight ESM™ - 32-bit
v5.1.7.6151.0 for ArcSight ESM™ - 64-bit

February 15, 2012



Release Notes for ArcSight Forwarding Connector

Copyright © 2012 Hewlett-Packard Development Company, L.P.

Confidential computer software. Valid license from HP required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

The information contained herein is subject to change without notice. The only warranties for HP products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. HP shall not be liable for technical or editorial errors or omissions contained herein.

Follow this link to see a complete statement of copyrights and acknowledgements:

<http://www.arcsight.com/copyrightnotice>

The network information used in the examples in this document (including IP addresses and hostnames) is for illustration purposes only.

This document is confidential.

Revision History

Date	Version	Description
02/15/2012	5.1.7.6154.0 (32-bit)	Support added for 64-bit JVM.
	5.1.7.6151.0 (64-bit)	

Release Notes template version: 2.1.0

Contact Information

Phone	1-866-535-3285 (North America) +44 (0)870 141 7487 (EMEA)
Support Web Site	http://support.openview.hp.com
Protect 724 Community	https://protect724.arcsight.com

ArcSight Forwarding Connector Release Notes

These release notes provide information for the current release of the ArcSight Forwarding Connector.

ArcSight ESM Forwarding Connector

The ArcSight ESM Forwarding Connector can receive events from a source ESM Manager and then send them to a secondary destination ESM Manager, a non-ESM location (such as HP Operations Manager), or to an ArcSight Logger.

What's New in the ArcSight Forwarding Connector

Support has been added for 64-bit JVM for the Windows and Linux platforms.

To Apply This Release

ArcSight recommends using the Forwarding Connector executable included with the corresponding ESM or HP integration release. Download and install the appropriate executable for your platform from the HP SSO site at <http://support.openview.hp.com>. Note that these version numbers are specific to Forwarding Connector releases, not release numbers of other ArcSight products.

The installation executables are:

- ArcSight-5.1.7.6154.0-SuperConnector-Linux.bin
- ArcSight-5.1.7.6154.0-SuperConnector-Win.exe
- ArcSight-5.1.7.6154.0-SuperConnector-AIX.bin
- ArcSight-5.1.7.6154.0-SuperConnector-Solaris.bin
- ArcSight-5.1.7.6151.0-SuperConnector-Linux.bin
- ArcSight-5.1.7.6151.0-SuperConnector-Win.exe

Known Issues

Number	Description
CON-11208	<p data-bbox="613 333 1227 386">Issue: Some certificates can be missing after Forwarding Connector upgrade.</p> <p data-bbox="613 401 1325 554">Workaround: If, after the upgrade of the Forwarding Connector, ESM does not forward events to the connector, check the <code>agent.log</code> file for this exception: <code>"sun.security.provider.certpath.SunCertPathBuilderException: unable to find valid certification path to requested target"</code>. If the exception exists, follow these steps:</p> <ol data-bbox="613 569 1325 695" style="list-style-type: none"><li data-bbox="613 569 857 590">1 Stop the connector.<li data-bbox="613 611 1325 663">2 See the <i>ArcSight ESM Administrator's Guide</i> for ESM Manager certificate import instructions.<li data-bbox="613 674 886 695">3 Restart the connector.
